

REVISION HISTORY

The following information provides a historical summary of the changes made to the BE1-79A hardware, firmware, and software. The corresponding revisions made to this instruction manual (9310200990) are also summarized. Revisions are listed in reverse chronological order.

Application Firmware Version and Date	Change
1.07, 02/08	<ul style="list-style-type: none">Modified firmware so the relay will go to Lockout after the EXIT command is entered through the RS-232 port or access has timed out. If the breaker is closed, the relay will go to Reset after the Lockout Timer expires.
1.05, 08/00	<ul style="list-style-type: none">SP-79ARS command mode parameters were changed from C (closed) and O (open) to E (energized) and D (de-energized).
1.03.XX, 08/98	<ul style="list-style-type: none">Coordinated open and close timing of outputs C5 and C6 to preserve consistent operation of the anti-pump function.
1.02.XX, 06/98	<ul style="list-style-type: none">Communication was made consistent with other Basler products by adding line feeds to ASCII data returned by the relay.
1.02.XX, 12/97	<ul style="list-style-type: none">Initial release of part number 9310200200.
1.01.XX, 07/97	<ul style="list-style-type: none">Initial release of part numbers 9310200100 and 9310200101.

Hardware Version and Date	Change
05/03	<ul style="list-style-type: none">Initial release of part number 9310200201.
08/00	<ul style="list-style-type: none">Added RS Contact Switch S5 for user-selection of normally-open or normally-closed RS contacts.
01/00	<ul style="list-style-type: none">Contact sensing jumpers added to the digital circuit board of relays with part number 9310200101 gave inputs V1, V2, V3, and V4 three specific ranges of operating voltage.
10/98	<ul style="list-style-type: none">Changed serialization format to HXXXXXXXXX.
12/97	<ul style="list-style-type: none">Initial release of part number 9310200200.
07/97	<ul style="list-style-type: none">Initial release of part numbers 9310200100 and 9310200101.

Manual Revision and Date	Change
G, 02/08	<ul style="list-style-type: none">Added manual part number and revision to footers.Updated <i>Output Contact</i> ratings in Section 1.Updated <i>Lockout</i> description in Section 3 to support version 1.07 firmware.Updated <i>Command Descriptions</i> in Section 4 to support version 1.07 firmware.